
#### **Computer Networks and the Internet**

Instructor: C. Pu (Ph.D., Assistant Professor)

Lecture 03

puc@marshall.edu





#### Complete Review Quiz I on Blackboard




- Two fundamental approaches to moving data through a network of links and switches
- packet-switched networks
  - resource not reserved
  - use resources on demand
  - may wait for access to commu. link
- circuit-switched networks
  - resource for communication reserved
    - between two end systems
    - for duration of the communication session
- simple analogy,
  - restaurant requires reservation "=" circuit-switched
  - restaurant requires no reservation "=" packet-switched


wait in buffer



- traditional telephone networks
  - circuit-switched networks
- what will happened if you want to talk to someone?
  - before sender sends information
    - must establishes the connection
    - switches maintain connection
      - connection is called **circuit**
  - When network establishes circuit
    - reserves a constant trans. rate
      - in network's link
      - for the duration of connection
    - transfer at the guaranteed rate








- what happens when transmit a packet over a packet-switched network?
  - packet sent into the network without reserving any link resources
  - if one of links is congested because other packets are transmitting over the link at the same time
    - packet will wait in a buffer and suffer a delay
- the Internet makes its best effort to deliver packets in a timely manner, but no guarantees




- network resources (e.g., bandwidth) divided into "pieces"
  - pieces allocated to calls (or communications)
  - resource piece is idle if not used by owning call (communications)
    - no sharing
- dividing link bandwidth into "pieces"
  - frequency division
  - time division





#### Circuit Switching: FDM and TDM

- circuit in a link is implemented with
  - frequency-division multiplexing (FDM)
    - the frequency spectrum of a link is divided up among the connections established across the link
    - the link dedicates a frequency band to each connection for the duration of connection
    - telephone networks: 4 kHz
    - FM radio: between 88 MHz and 108 MHz
  - time-division multiplexing (TDM)
    - time is divided into frames of fixed duration, and each frame is divided into a fixed number of time slots
    - when establishing a connection, dedicating one time slot in every frame to the connection
    - slots are dedicated for the sole use of that connection, to transmit the connection's data



### Circuit Switching: Argument

- circuit switching is wasteful because dedicated circuits are idle during silent periods
  - e.g.,
    - One person in a telephone call stops talking
      - resources can't be used by other ongoing connections
    - Radiologist remotely access a series of x-rays
      - setup connection
      - request an image
      - contemplate the image but, not using network resources
      - request a new image
- circuit switching requires extra effort to establish circuits and reserve end-to-end trans. capacity, complex signaling software to coordinate the operation of switches



### Circuit Switching: Numerical Example

- How long does it take to send a file of 640,000 bits from host A to host B over a circuit-switched network?
  - all links are 1.536 Mbps
  - each link uses TDM with 24 slots/sec
  - 500 msec to establish end-to-end circuit
  - Answer:
    - each circuit has a trans. rate of I.536 Mbps / 24 = 64 kbps
    - trans. file: 640,000 bits / 64 kbps = 10 seconds
    - total time: 10 seconds + 500 msec = 10.5 seconds



#### Packet Switching Vs. Circuit Switching


- Critics of packet switching
  - not suitable for real-time switching, e.g., telephone call, video conference calls
    - variable and unpredictable end-to-end delays
- Proponents of packet switching
  - better sharing of trans. capacity
  - simpler, more efficient, and less costly
- Generally, packet switching is more efficient. Why???



#### Packet Switching Vs. Circuit Switching

#### Packet switching allows more users to use network!

- I Mbps link
- suppose one user generates one thousand 1000-bit packet out of 10 users
  - 9 users remain quiet
- **TDM** circuit-switching:
  - e.g., 10 time slots per frame
  - the active user can only use its one time slot per frame
  - support 10 simultaneous users
- packet switching:
  - The active users can continuously send its packet at the full link rate of I Mbps





# Packet Switching Vs. Circuit Switching (cont.)

Is packet switching a "slam dunk winner?"


- great for burst data
  - resource sharing
  - simpler, no call setup
- excessive congestion: packet delay and loss
  - protocols needed for reliable data transfer, congestion control
- Q: how to provide circuit-like behavior?
  - bandwidth guarantees needed for audio/video apps
  - still an unsolved problem




#### **Internet Structure: Network of Networks**

- End systems connect to the Internet via an access ISPs (Internet Service Providers)
  - wired or wireless connectivity
    - DSL, cable, FTTH, Wi-Fi, and cellular
  - residential, company, and university ISPs
- Access ISPs in turn must be interconnected
  - so that any two hosts can send packets to each other
- Resulting network of networks is very complex
  - evolution was driven by economics and national policies










#### Internet Structure: Network of Networks (cont.)

Option: connect each access ISP to a global transit ISP? Customer and provider ISPs have economic agreement.









#### Internet Structure: Network of Networks (cont.)


... and regional networks may arise to connect access nets to ISPS



#### Internet Structure: Network of Networks (cont.)

... and content provider networks (e.g., Google, Microsoft, Akamai) may run their own network, to bring services, content close to end users





at center: small # of well-connected large networks

- "tier-I" commercial ISPs (e.g., Level 3, Sprint, AT&T, NTT), national & international coverage
- content provider network (e.g., Google)

